



شرکت مهندسی شبکه
پال نت

فعال سازی لایسنس سرور ترمینال سرویس Windows Server 2013



سهروردی شمالی - خیابان خلیل حسینی (سورنا) - کوچه آریا وطنی - پلاک ۲۲ - واحد ۶

۰۲۱ - ۸۸۷۶۰۹۵۵ www.palnetgroup.ir


info@palnetgroup.ir

Activating Remote Desktop Licensing in Windows Server 2012

فعال سازی لایسنس ترمینال سرور ۲۰۱۲


1. To Activate the Licensing Server, Launch Remote Desktop Licensing Manager.

۱. برای فعال سازی لایسنس ابتدا قسمت Remote Desktop Licensing را باز کنید.




2. Right Click on the server and select activate server.

۲. روی سرور کلیک راست بزنید و activate server را انتخاب کنید.




3. Click Next.

۳. گزینه Next را بزنید.




4. Choose your method of activation, I am choosing Web Browser, Click Next.

۴. روش فعال سازی خود را انتخاب کنید ، من Web Browser را انتخاب کردم و سپس گزینه Next را بزنید.




5. Click on the Link to open the activation page.

۵. لینک را جهت باز کردن صفحه فعال سازی انتخاب کنید.



6. Select Activate a license server, Click Next.

۶. Activate a license server انتخاب کنید و سپس گزینه Next را بزنید.



7. Enter the required information. Click Next.

۷. **required information** را وارد کنید و سپس **Next** بزنید.



Windows Server
Remote Desktop Services

Home FAQ Help

To activate your license server, you need to provide the following information. Your product ID can be found by selecting Activate Server in the Remote Desktop Licensing Manager tool.

Required information is denoted by a red asterisk (*).

Product Information

Product ID:
00184-40000-00001-AT148 *

Company Information

Last/Surname: Pathan * First/Given Name: Aasim *

Company: WackyTechTips Country/Region: India *

Organizational Unit:

Postal Address: Phone Number:

8. Verify the information, Click Next.

۸. **اطلاعات را بررسی کنید و سپس Next** بزنید.

correct, and then click Next. If you need to make corrections, click Back.

Product Information

Product ID:
00184-40000-00001-AT148

Company Information

Last/Surname:
Pathan

First/Given Name:
Aasim

Company:
WackyTechTips

Organizational Unit:

E-Mail Address:

Phone Number:

Company Address:

City:

State/Province:

Postal Code:

Country/Region:
India

Back Next

9. Copy the License server ID.

۹. ID لایسنس سرور را کپی کنید.

Your license server activation request was successfully processed. Print this page for reference.

Your license server ID, which you need to enter in the Remote Desktop License Server Activation Wizard, is:

PFDTY-G79WK-7T67J-WW324-WGXD3-4W89F-HQBJ7

Do you wish to install client access licenses now on the license server with this product ID?
00184-40000-00001-AT148



10. Paste the License server ID in the given field. Click Next.

۱۰. ID لایسنس سرور را در این قسمت وارد کنید و سپس Next بزنید.

Activate Server Wizard
x

License Server Activation
 Enter the license server ID.


To activate your license server, go to the Remote Desktop Licensing Web Site located at:
<https://activate.microsoft.com>

You will need your Product ID to complete this operation. Your Product ID is:

00184-40000-00001-AT148

After you complete the transaction on the Remote Desktop Licensing Web Site, type the license server ID in the following boxes.

PFDTY	G79WK	7T67J	WW324	WGXD3	4W89F	HQBJ7
-------	-------	-------	-------	-------	-------	-------



11. Uncheck Start Install Licenses Wizard now. As we do not require any Client licenses. Click Finish.

۱۱. در حال حاضر قسمت Start Install Licenses Wizard را تیک نزنید چون که نیاز به لایسنس کلاینت نداریم و در پایان گزینه پایان را بزنید.



تهیه شده در:

واحد تحقیق و توسعه

شرکت مهندسی شبکه پال نت

ارائه دهنده لایسنس ترمینال سرور ویندوز سرور ۲۰۰۸ و ۲۰۱۲

www.palnetgroup.ir